

ViaBTC XMR挖矿教程

1. 下载XMR-STAK软件：<https://github.com/fireice-uk/xmr-stak/releases>

2. 下载完后直接运行xmr stak的应用程序

3. 运行后，输入数字0,如图：

```
Please enter:
- Do you want to use the HTTP interface?
Unlike the screen display, browser interface is not affected by the GPU lag.
If you don't want to use it, please enter 0, otherwise enter port number that the miner should listen
0
Configuration stored in file 'config.txt'
Please enter:
- Please enter the currency that you want to mine:
  - aeon7
  - bbscoin
  - bittube
  - cryptonight
  - cryptonight_bittube2
  - cryptonight_masari
  - cryptonight_haven
  - cryptonight_heavy
  - cryptonight_lite
  - cryptonight_lite_v7
  - cryptonight_lite_v7_xor
  - cryptonight_superfast
  - cryptonight_v7
  - cryptonight_v8
  - cryptonight_v7_stellite
  - freehaven
  - graft
  - haven
  - intense
  - masari
  - monero
  - qrl
  - ryo
  - stellite
  - turtlecoin
cryptonight_v8
```

4. 输入币种：**cryptonight_v8**，用来挖XMR

5.按以下图文提示，输入相应的矿池端口、钱包地址、密码等信息，完成后即可开始挖矿了。

注意：80端口也可以使用

```
cryptonight_v8
- Pool address: e.g. pool.example.com:3333
xmr.viabtc.com:8888 ← 输入: xmr.viabtc.com:8888
- Username (wallet address or pool login):
xyang ← 输入用户名或钱包地址
- Password (mostly empty or x):
x ← 输入x
- Rig identifier for pool-side statistics (needs pool support). Can be empty:
 ← 敲空格
- Does this pool port support TLS/SSL? Use no if unknown. (y/N)
N ←
- Do you want to use nicehash on this pool? (y/n)
n ←
- Do you want to use multiple pools? (y/n)
n ← 三处均输入: n
Pool configuration stored in file 'pools.txt'
[2019-01-14 16:25:37] : Your CPU doesn't support hardware AES. Don't expect high hashrates.
[2019-01-14 16:25:37] : Elevating because we need to set up fast memory privileges.
[2019-01-14 16:25:44] : This window has been opened because xmr-stak needed to run as adminis
now.
```